Calling Conventions


Hakim Weatherspoon

CS 3410, Spring 2013


Computer Science

Cornell University

Big Picture: Where are we now?



Big Picture: Where are we going?



Goals for Today

Calling Convention for Procedure Calls Enable code to be reused by allowing code snippets to be invoked

Will need a way to

- call the routine (i.e. transfer control to procedure)
- pass arguments
 - fixed length, variable length, recursively
- return to the caller
 - Putting results in a place where caller can find them
- Manage register

Cheat Sheet and Mental Model for Today

- first four arg words passed in \$a0, \$a1, \$a2, \$a3
- remaining arg words passed in parent's stack frame
- return value (if any) in \$v0, \$v1
- stack frame at \$sp
 - contains \$ra (clobbered on JAL to sub-functions)

contains local vars (possibly clobbered by sub-functions)

- contains extra arguments to sub-functions

 contains space for first 4 arguments to sub-functions

 callee save regs are preserved


caller save regs are not

Global data accessed via \$gp

	locals
Śsn→	outgoing args

\$fp →	saved ra
	saved fp
nctions	saved regs
	(\$s0 \$s7)

Cheat Sheet and Mental Model for Today




How do we share registers and use memory when making procedure calls'

What is the convention to call a subroutine?


```
int main (int argc, char* argv[ ]) {
     int n = 9;
     int result = multi(n);
}
int multi(int n) {
      int f = 1;
      int i = 1;
      int j = n - 1;
      while(j >= 0) {
            f *= i;
            i++;
            j = n - 1;
      return f;
```

Procedure Call – Attempt #1: Use Jumps



Jumps and branches can transfer control to the callee (called procedure) Jumps and branches can transfer control back

Procedure Call – Attempt #1: Use Jumps




Jumps and branches can transfer control to the callee (called procedure) Jumps and branches can transfer control back

What happens when there are multiple calls from different call sites?


Takeaway1: Need Jump And Link

JAL (Jump And Link) instruction moves a new value into the PC, and simultaneously saves the old value in register \$31 (aka \$ra or return address)

Thus, can get back from the subroutine to the instruction immediately following the jump by transferring control back to PC in register \$31



JAL saves the PC in register \$31
Subroutine returns by jumping to \$31
What happens for recursive invocations?




JAL saves the PC in register \$31
Subroutine returns by jumping to \$31
What happens for recursive invocations?

```
int main (int argc, char* argv[ ]) {
     int n = 9;
     int result = multi(n);
int multi(int n) {
      int f = 1;
      int i = 1;
      int j = n - 1;
      while(j >= 0) {
            f *= i;
            i++;
            j = n - 1;
      return f;
```

```
int main (int argc, char* argv[]) {
   int n = 9;
   int result = multi(n);
}
```

What happens for recursive invocations?

```
int multi(int n) {
    if(n == 0) {
        return 1;
    } else {
        return n * multi(n - 1)
    }
}
```



What happens for recursive invocations?

Recursion overwrites contents of \$31

Need to save and restore the register contents

Need a "Call Stack"

Call stack

 contains activation records (aka stack frames)

Each activation record contains


- the return address for that invocation
- the local variables for that procedure

A stack pointer (sp) keeps track of the top of the stack

dedicated register (\$29) on the MIPS

Manipulated by push/pop operations

- push: move sp down, store
- pop: load, move sp up



Need a "Call Stack"

Call stack

 contains activation records (aka stack frames)

Each activation record contains


- the return address for that invocation
- the local variables for that procedure

A stack pointer (sp) keeps track of the top of the stack

dedicated register (\$29) on the MIPS

Manipulated by push/pop operations

- push: move sp down, store
- pop: load, move sp up




Stack Growth

(Call) Stacks start at a high address in memory


Stacks grow down as frames are pushed on

- Note: data region starts at a low address and grows up
- The growth potential of stacks and data region are not artificially limited

Anatomy of an executing program



Anatomy of an executing program




Takeaway2: Need a Call Stack

JAL (Jump And Link) instruction moves a new value into the PC, and simultaneously saves the old value in register \$31 (aka \$ra or return address) Thus, can get back from the subroutine to the instruction immediately following the jump by transferring control back to PC in register \$31


Need a Call Stack to return to correct calling procedure. To maintain a stack, need to store an *activation record* (aka a "stack frame") in memory. Stacks keep track of the correct return address by storing the contents of \$31 in memory (the stack).

Attempt #3: JAL/JR with Activation Records



Stack used to save and restore contents of \$31

Attempt #3: JAL/JR with Activation Records



Stack used to save and restore contents of \$31 How about arguments?

Next Goal

Need consistent way of passing arguments and getting the result of a subroutine invocation

Attempt #4: Arguments & Return Values

Need consistent way of passing arguments and getting the result of a subroutine invocation

Given a procedure signature, need to know where arguments should be placed

• int min(int a, int b);

• int subf(int a, int b, int c, int d, int e);

• int isalpha(char c);

• int treesort(struct Tree *root);

• struct Node *createNode();

• struct Node mynode();

• struct Node mynode();

Too many combinations of char, short, int, void *, struct, etc.

MIPS treats char, short, int and void * identically

\$v0, \$v1

Simple Argument Passing

```
main:
li $a0, 6
li $a1, 7
jal min
// result in $v0
```

First four arguments are passed in registers

Specifically, \$4, \$5, \$6 and \$7, aka \$a0, \$a1, \$a2, \$a3

The returned result is passed back in a register

Specifically, \$2, aka \$v0

Conventions so far:

- args passed in \$a0, \$a1, \$a2, \$a3
- return value (if any) in \$v0, \$v1
- stack frame at \$sp
 - contains \$ra (clobbered on JAL to sub-functions)


Q: What about argument lists?


Many Arguments

main:
li \$a0, 0
li \$a1, 1
li \$a2, 2
li \$a3, 3
jal subf
// result in \$v0

What if there are more than 4 arguments?

Many Arguments







What if there are more than 4 arguments?

Use the stack for the additional arguments

"spill"

Many Arguments





What if there are more than 4 arguments?

Use the stack for the additional arguments

• "spill"

Variable Length Arguments

```
printf("Coordinates are: %d %d %d\n", 1, 2, 3);
```

Could just use the regular calling convention, placing first four arguments in registers, spilling the rest onto the stack


- Callee requires special-case code
- if(argno == 1) use a0, ... else if (argno == 4) use a3, else use stack offset

Best to use an (initially confusing but ultimately simpler) approach:

- Pass the first four arguments in registers, as usual
- Pass the rest on the stack
- Reserve space on the stack for all arguments, including the first four
 Simplifies functions that use variable-length arguments
 - Store a0-a3 on the slots allocated on the stack, refer to all argument

Register Layout on Stack

main: li \$a0, 0 li \$a1, 1 li \$a2, 2 li \$a3, 3 addiu \$sp,s\$p,-24 li \$8, 4 sw \$8, 16(\$sp) li \$8, 5 sw \$8, 20(\$sp) jal subf // result in\$ v0




First four arguments

16(\$sp)
12(\$sp)
8(\$sp)
The rest are on the
stack

0(\$sp)
There is room on

There is room on the stack for the first four arguments, just in case

Frame Layout on Stack




```
blue() {
    pink(0,1,2,3,4,5);
}
```

Frame Layout on Stack

	return address
	5
	4
	space for \$a3
	space for \$a2
	space for \$a1
-	space for \$a0
sp	return address
sp	

```
blue() {
    pink(0,1,2,3,4,5);
}
pink(int a, int b, int c, int d, int e, int f) {
    ...
}
```

Frame Layout on Stack



Conventions so far:

- first four arg words passed in \$a0, \$a1, \$a2, \$a3
- remaining arg words passed on the stack
- return value (if any) in \$v0, \$v1
- stack frame at \$sp
 - contains \$ra (clobbered on JAL to sub-functions)
 - contains extra arguments to sub-functions
 - contains space for first 4 arguments to sub-functions

MIPS Register Conventions so far:

r0	\$zero	zero	r16			Pseudo-Instructions
_r1	\$at	assembler temp	r17			e.g. BLZ
r2	\$v0	function	r18			
r3	\$v1	return values	r19			SLT \$at
r4	\$a0		r20			BNE \$at, 0, L
r5	\$a1	function	r21			
r6	\$a2	arguments	r22			
r7	\$a3		r23			
r8			r24			
r9			r25			
r10			r26	\$k0		reserved
r11			r27	\$k1	fo	or OS kernel
r12			r28			
r13			r29			
r14			r30			
r15			r31	\$ra	ret	turn address

Java vs C: Pointers and Structures

Pointers are 32-bits, treat just like ints

Pointers to structs are pointers

C allows passing whole structs

- \$a0,\$a1 \$a2,\$a3 int distance(struct Point p1, struct Point p2)
- Treat like a collection of consecutive 32-bit arguments, use registers for first 4 words, stack for rest
- Of course, Inefficient and to be avoided, better to use int distance(struct Point *p1, struct Point *p2) \$a0 in all cases

Globals and Locals

Global variables are allocated in the "data" region of the program

• Exist for all time, accessible to all routines

Local variables are allocated within the stack frame

Exist solely for the duration of the stack frame

Dangling pointers are pointers into a destroyed stack frame

- C lets you create these, Java does not
- int *foo() { int a; return(&a)}

Return the address of a, But a is stored on stack, so will be removed when call returns and point will be invalid

Global and Locals

How does a function load global data?

global variables are just above 0x10000000

Convention: *global pointer*

- \$28 is \$gp (pointer into *middle* of global data section)
 \$gp = 0x10008000
- Access most global data using LW at \$gp +/- offset LW \$v0, 0x8000(\$gp)
 LW \$v1, 0x7FFF(\$gp)

Anatomy of an executing program

1	, <u> </u>	
0xffffffc		top
	system reserved	
0x80000000		
0x7ffffffc	stack	
\$gp	dynamic data (heap)	
0x10000000	static data	
0x00400000	code (text)	_
0x0000000	system reserved	bottom

Frame Pointer

It is often cumbersome to keep track of location of data on the stack

 The offsets change as new values are pushed onto and popped off of the stack

Keep a pointer to the top of the stack frame

Simplifies the task of referring to items on the stack

A frame pointer, \$30, aka \$fp

- Value of \$sp upon procedure entry
- Can be used to restore \$sp on exit

Conventions so far

- first four arg words passed in \$a0, \$a1, \$a2, \$a3
- remaining arg words passed in parent's stack frame
- return value (if any) in \$v0, \$v1
- stack frame at \$sp
 - contains \$ra (clobbered on JAL to sub-functions)
 - contains extra arguments to sub-functions
 - contains space for first 4 arguments
 to sub-functions

Next Goal

What convention should we use to share use of registers across procedure calls?

Register Usage

Suppose a routine would like to store a value in a register Two options: callee-save and caller-save

Callee-save:

- Assume that one of the callers is already using that register to hold a value of interest
- Save the previous contents of the register on procedure entry, restore just before procedure return
- E.g. \$31

Caller-save:

- Assume that a caller can clobber any one of the registers
- Save the previous contents of the register before proc call
- Restore after the call

MIPS calling convention supports both

Callee-Save

```
main:
addiu $sp.$sp.-32
 sw $31,28($sp)
 sw $30, 24($sp)
 sw $17, 20($sp)
 sw $16, 16($sp)
addiu $30, $sp, 28
 [use $16 and $17]
 lw $31,28($sp)
 lw $30,24($sp)
 lw $17, 20$sp)
 lw $16, 16($sp)
addiu $sp,$sp,32
jr $31
```

Assume caller is using the registers Save on entry, restore on exit

Pays off if caller is actually using the registers, else the save and restore are wasted

Callee-Save

```
main:
    addiu $sp,$sp,-32
    sw $ra,28($sp)
    sw $fp, 24($sp)
    sw $s1, 20($sp)
    sw $s0, 16($sp)
    addiu $fp, $sp, 28
    ...
    [use $s0 and $s1]

lw $ra,28($sp)
    lw $fp,24($sp)
    lw $s1, 20$sp)
    lw $s0, 16($sp)
```

addiu \$sp,\$sp,32

ir \$ra

Assume caller is using the registers Save on entry, restore on exit

Pays off if caller is actually using the registers, else the save and restore are wasted

Caller-Save

```
main:
 [use $8 & $9]
 addiu $sp,$sp,-8
 sw $9, 4($sp)
 sw $8, 0($sp)
 ial mult
 lw $9, 4($sp)
 lw $8, 0($sp)
 addiu $sp,$sp,8
 [use $8 & $9]
```

Assume the registers are free for the taking, clobber them

But since other subroutines will do the same, must protect values that will be used later

By saving and restoring them before and after subroutine invocations

Pays off if a routine makes few calls to other routines with values that need to be preserved

Caller-Save

```
main:
 [use $t0 & $t1]
 addiu $sp,$sp,-8
 sw $t1, 4($sp)
 sw $t0, 0($sp)
 ial mult
 lw $t1, 4($sp)
 lw $t0, 0($sp)
 addiu $sp,$sp,8
 [use $t0 & $t1]
```

Assume the registers are free for the taking, clobber them

But since other subroutines will do the same, must protect values that will be used later


By saving and restoring them before and after subroutine invocations

Pays off if a routine makes few calls to other routines with values that need to be preserved


		ADDILL Con Con 22	# all a sata france
fp	saved ra	ADDIU \$sp, \$sp, -32	
	saved fp	SW \$ra, 28(\$sp)	# save \$ra
	saved regs	SW \$fp, 24(\$sp)	# save old \$fp
	(\$s0 \$s7)	SW \$s1, 20(\$sp)	# save
	. ,	SW \$s0, 16(\$sp)	# save
	locals	ADDIU \$fp, \$sp, 28	# set new frame ptr
sp		•••	•••
	outgoing	BODY	
	args	•••	•••
		LW \$s0, 16(\$sp)	# restore
		LW \$s1, 20(\$sp)	# restore
		LW \$fp, 24(\$sp)	# restore old \$fp
		LW \$ra, 28(\$sp)	# restore \$ra

JR \$ra


ADDIU \$sp,\$sp, 32 # dealloc frame




```
blue() {
   pink(0,1,2,3,4,5);
}
```



```
blue() {
    pink(0,1,2,3,4,5);
}
pink(int a, int b, int c, int d, int e, int f) {
    orange(10,11,12,13,14);
}
```



Buffer Overflow



MIPS Register Recap

Return address: \$31 (ra)

Stack pointer: \$29 (sp)

Frame pointer: \$30 (fp)

First four arguments: \$4-\$7 (a0-a3)

Return result: \$2-\$3 (v0-v1)

Callee-save free regs: \$16-\$23 (s0-s7)

Caller-save free regs: \$8-\$15,\$24,\$25 (t0-t9)

Reserved: \$26, \$27

Global pointer: \$28 (gp)

Assembler temporary: \$1 (at)

MIPS Register Conventions

r0	\$zero	zero	r16	\$s0	
r1	\$at	assembler temp	r17	\$s1	
r2	\$v0	function	r18	\$s2	
r3	\$v1	return values	r19	\$s3	saved
r4	\$a0		r20	\$s4	(callee save)
r5	\$a1	function	r21	\$s5	
r6	\$a2	arguments	r22	\$s6	
r7	\$a3		r23	\$s7	
r8	\$t0		r24	\$t8	more temps
r9	\$t1		r25	\$t9	(caller save)
r10	\$t2		r26	\$k0	reserved for
<u>r11</u>	\$t3	temps	r27	\$k1	kernel
r12	\$t4	(caller save)	r28	\$gp	global data pointer
r13	\$t5	,	r29	\$sp	stack pointer
r14	\$t6		r30	\$fp	frame pointer
r15	\$t7		r31	\$ra	return address

Recap: Conventions so far

- first four arg words passed in \$a0, \$a1, \$a2, \$a3
- remaining arg words passed in parent's stack frame
- return value (if any) in \$v0, \$v1
- stack frame at \$sp
 - contains \$ra (clobbered on JAL to sub-functions)

 contains local vars (possibly clobbered by sub-functions)

contains extra arguments to sub-functions

 contains space for first 4 arguments to sub-functions

 callee save regs are preserved

caller save regs are not

Global data accessed via \$gp

	locals
Śsn→	outgoing args

$Sfp \rightarrow$	saved ra
	saved fp
ctions	saved regs
	(\$s0 \$s7)