

# Spline Curves

CS 4620 Lecture 18

## Motivation: smoothness


- In many applications we need smooth shapes
  - that is, without discontinuities



- So far we can make
  - things with corners (lines, squares, rectangles, ...)
  - circles and ellipses (only get you so far!)

## Classical approach

- Pencil-and-paper draftsmen also needed smooth curves
- Origin of “spline:” strip of flexible metal
  - held in place by pegs or weights to constrain shape
  - traced to produce smooth contour



## Translating into usable math


- Smoothness
  - in drafting spline, comes from physical curvature minimization
  - in CG spline, comes from choosing smooth functions
    - usually low-order polynomials
- Control
  - in drafting spline, comes from fixed pegs
  - in CG spline, comes from user-specified *control points*

## Defining spline curves

- At the most general they are parametric curves

$$S = \{\mathbf{p}(t) \mid t \in [0, N]\}$$

- Generally  $f(t)$  is a piecewise polynomial
  - for this lecture, the discontinuities are at the integers



## Defining spline curves


- Generally  $f(t)$  is a piecewise polynomial
  - for this lecture, the discontinuities are at the integers
  - e.g., a cubic spline has the following form over  $[k, k + 1]$ :

$$x(t) = a_x t^3 + b_x t^2 + c_x t + d_x$$


$$y(t) = a_y t^3 + b_y t^2 + c_y t + d_y$$

- Coefficients are different for every interval

## Coordinate functions




## Coordinate functions



## Control of spline curves


- Specified by a sequence of control points
- Shape is guided by control points (aka control polygon)
  - interpolating: passes through points
  - approximating: merely guided by points



## How splines depend on their controls


- Each coordinate is separate
  - the function  $x(t)$  is determined solely by the  $x$  coordinates of the control points
  - this means 1D, 2D, 3D, ... curves are all really the same
- Spline curves are **linear** functions of their controls
  - moving a control point two inches to the right moves  $x(t)$  twice as far as moving it by one inch
  - $x(t)$ , for fixed  $t$ , is a linear combination (weighted sum) of the control points'  $x$  coordinates
  - $\mathbf{p}(t)$ , for fixed  $t$ , is a linear combination (weighted sum) of the control points

## Splines as reconstruction



## Trivial example: piecewise linear

- This spline is just a polygon
  - control points are the vertices
- But we can derive it anyway as an illustration
- Each interval will be a linear function
  - $x(t) = at + b$
  - constraints are values at endpoints
  - $b = x_0$ ;  $a = x_1 - x_0$
  - this is linear interpolation



## Trivial example: piecewise linear

- Vector formulation

$$x(t) = (x_1 - x_0)t + x_0$$

$$y(t) = (y_1 - y_0)t + y_0$$

$$\mathbf{p}(t) = (\mathbf{p}_1 - \mathbf{p}_0)t + \mathbf{p}_0$$

- Matrix formulation

$$\mathbf{p}(t) = \begin{bmatrix} t & 1 \end{bmatrix} \begin{bmatrix} -1 & 1 \\ 1 & 0 \end{bmatrix} \begin{bmatrix} \mathbf{p}_0 \\ \mathbf{p}_1 \end{bmatrix}$$

## Trivial example: piecewise linear

- Basis function formulation

- regroup expression by  $\mathbf{p}$  rather than  $t$


$$\begin{aligned} \mathbf{p}(t) &= (\mathbf{p}_1 - \mathbf{p}_0)t + \mathbf{p}_0 \\ &= (1 - t)\mathbf{p}_0 + t\mathbf{p}_1 \end{aligned}$$

- interpretation in matrix viewpoint

$$\mathbf{p}(t) = \left( \begin{bmatrix} t & 1 \end{bmatrix} \begin{bmatrix} -1 & 1 \\ 1 & 0 \end{bmatrix} \right) \begin{bmatrix} \mathbf{p}_0 \\ \mathbf{p}_1 \end{bmatrix}$$


## Trivial example: piecewise linear

- Vector blending formulation: “average of points”
  - blending functions: contribution of each point as  $t$  changes



## Trivial example: piecewise linear


- Basis function formulation: “function times point”
  - basis functions: contribution of each point as  $t$  changes



- can think of them as blending functions glued together
- this is just like a reconstruction filter!


## Seeing the basis functions

- Basis functions of a spline are revealed by how the curve changes in response to a change in one control
  - to get a graph of the basis function, start with the curve laid out in a straight, constant-speed line
    - what are  $x(t)$  and  $y(t)$ ?
  - then move one control straight up



## Hermite splines

- Less trivial example
- Form of curve: piecewise cubic
- Constraints: endpoints and tangents (derivatives)



## Hermite splines

- Solve constraints to find coefficients

$$x(t) = at^3 + bt^2 + ct + d$$

$$x'(t) = 3at^2 + 2bt + c$$

$$x(0) = x_0 = d$$

$$x(1) = x_1 = a + b + c + d$$

$$x'(0) = x'_0 = c$$

$$x'(1) = x'_1 = 3a + 2b + c$$

$$d = x_0$$

$$c = x'_0$$

$$a = 2x_0 - 2x_1 + x'_0 + x'_1$$

$$b = -3x_0 + 3x_1 - 2x'_0 - x'_1$$

## Hermite splines

- Matrix form is much simpler

$$\mathbf{p}(t) = \begin{bmatrix} t^3 & t^2 & t & 1 \end{bmatrix} \begin{bmatrix} 2 & -2 & 1 & 1 \\ -3 & 3 & -2 & -1 \\ 0 & 0 & 1 & 0 \\ 1 & 0 & 0 & 0 \end{bmatrix} \begin{bmatrix} \mathbf{p}_0 \\ \mathbf{p}_1 \\ \mathbf{v}_0 \\ \mathbf{v}_1 \end{bmatrix}$$

– coefficients = rows

– basis functions = columns


- note  $\mathbf{p}$  columns sum to  $[0\ 0\ 0\ 1]^T$

## Longer Hermite splines

- Can only do so much with one Hermite spline
- Can use these splines as segments of a longer curve
  - curve from  $t = 0$  to  $t = 1$  defined by first segment
  - curve from  $t = 1$  to  $t = 2$  defined by second segment
- To avoid discontinuity, match derivatives at junctions
  - this produces a  $C^1$  curve


## Hermite splines

- Hermite blending functions




## Hermite splines

- Hermite basis functions



## Continuity


- Smoothness can be described by degree of continuity
  - zero-order ( $G^0$ ): position matches from both sides
  - first-order ( $G^1$ ): tangent also matches from both sides
  - second-order ( $G^2$ ): curvature also matches from both sides
  - $G^n$  vs.  $C^n$



## Continuity

- Parametric continuity ( $C$ )
  - is continuity of coordinate functions, e.g.,  $x(t)$ ,  $y(t)$ ,  $z(t)$
- Geometric continuity ( $G$ )
  - is continuity of the geometric curve itself
- Neither form of continuity is guaranteed by the other
  - Can be  $C^1$  but not  $G^1$  when  $\mathbf{p}(t)$  comes to a halt (next slide)
  - Can be  $G^1$  but not  $C^1$  when the tangent vector changes length abruptly

## Geometric vs. parametric continuity



## Continuity

$$\mathbf{p}^{(n)}(t) = \frac{d^n \mathbf{p}(t)}{dt^n}$$

- A curve is said to be  $C^n$  continuous if  $\mathbf{p}(t)$  is continuous, and all derivatives of  $\mathbf{p}(t)$  up to and including degree  $n$  have the same direction and magnitude:

$$\lim_{x \rightarrow t_-} \mathbf{p}^{(m)}(x) = \lim_{x \rightarrow t_+} \mathbf{p}^{(m)}(x), \quad m = 0 \dots n$$


- $G^n$  continuity is like  $C^n$  but only requires the derivatives to have the same direction:

$$\lim_{x \rightarrow t_-} \mathbf{p}^{(n)}(x) = k \lim_{x \rightarrow t_+} \mathbf{p}^{(n)}(x), \quad \text{for some } k > 0$$

- Alternately, a curve is  $G^n$  continuous if it can be reparameterized to be  $C^n$  continuous
  - i.e., there exists  $t=a(\tau)$ , such that  $\mathbf{q}(\tau)=\mathbf{p}(a(\tau))$  is  $C^n$  continuous


## Control

- Local control
  - changing control point only affects a limited part of spline
  - without this, splines are very difficult to use
  - many likely formulations lack this
    - polynomial fits
    - natural cubic spline (e.g., see [Cheney and Kincaid])
      - Continuous  $\mathbf{p}$ ,  $\mathbf{p}^{(1)}$ ,  $\mathbf{p}^{(2)}$ , with  $\mathbf{p}^{(2)}=0$  at endpoints
      - Global tridiagonal solve for coefficients




## Control

- Convex hull property
  - convex hull = smallest convex region containing points
    - think of a rubber band around some pins
  - some splines stay inside convex hull of control points
    - simplifies clipping, culling, picking, etc.



## Affine invariance

- Transforming the control points is the same as transforming the curve
  - true for all commonly used splines
  - extremely convenient in practice...



## Matrix form of spline


$$\mathbf{p}(t) = \mathbf{a}t^3 + \mathbf{b}t^2 + \mathbf{c}t + \mathbf{d}$$

$$\begin{bmatrix} t^3 & t^2 & t & 1 \end{bmatrix} \begin{bmatrix} \times & \times & \times & \times \\ \times & \times & \times & \times \\ \times & \times & \times & \times \\ \times & \times & \times & \times \end{bmatrix} \begin{bmatrix} \mathbf{p}_0 \\ \mathbf{p}_1 \\ \mathbf{p}_2 \\ \mathbf{p}_3 \end{bmatrix}$$

$$\mathbf{p}(t) = b_0(t)\mathbf{p}_0 + b_1(t)\mathbf{p}_1 + b_2(t)\mathbf{p}_2 + b_3(t)\mathbf{p}_3$$


## Hermite splines

- Constraints are endpoints and endpoint tangents




$$\mathbf{p}(t) = \begin{bmatrix} t^3 & t^2 & t & 1 \end{bmatrix} \begin{bmatrix} 2 & -2 & 1 & 1 \\ -3 & 3 & -2 & -1 \\ 0 & 0 & 1 & 0 \\ 1 & 0 & 0 & 0 \end{bmatrix} \begin{bmatrix} \mathbf{p}_0 \\ \mathbf{p}_1 \\ \mathbf{v}_0 \\ \mathbf{v}_1 \end{bmatrix}$$

## Hermite basis



## Affine invariance


- Basis functions associated with points should always sum to 1



$$\begin{aligned} \mathbf{p}(t) &= b_0\mathbf{p}_0 + b_1\mathbf{p}_1 + b_2\mathbf{v}_0 + b_3\mathbf{v}_1 \\ \mathbf{p}'(t) &= b_0(\mathbf{p}_0 + \mathbf{u}) + b_1(\mathbf{p}_1 + \mathbf{u}) + b_2\mathbf{v}_0 + b_3\mathbf{v}_1 \\ &= b_0\mathbf{p}_0 + b_1\mathbf{p}_1 + b_2\mathbf{v}_0 + b_3\mathbf{v}_1 + (b_0 + b_1)\mathbf{u} \\ &= \mathbf{p}(t) + \mathbf{u} \end{aligned}$$

## Hermite to Bézier


- Mixture of points and vectors is awkward
- Specify tangents as differences of points



- note derivative is defined as 3 times offset
  - reason is illustrated by linear case

## Hermite to Bézier

$$\begin{aligned} \mathbf{p}_0 &= \mathbf{q}_0 \\ \mathbf{p}_1 &= \mathbf{q}_3 \\ \mathbf{v}_0 &= 3(\mathbf{q}_1 - \mathbf{q}_0) \\ \mathbf{v}_1 &= 3(\mathbf{q}_3 - \mathbf{q}_2) \end{aligned}$$



$$\begin{bmatrix} \mathbf{a} \\ \mathbf{b} \\ \mathbf{c} \\ \mathbf{d} \end{bmatrix} = \begin{bmatrix} -1 & 3 & -3 & 1 \\ 3 & -6 & 3 & 0 \\ -3 & 3 & 0 & 0 \\ 1 & 0 & 0 & 0 \end{bmatrix} \begin{bmatrix} \mathbf{q}_0 \\ \mathbf{q}_1 \\ \mathbf{q}_2 \\ \mathbf{q}_3 \end{bmatrix}$$

## Bézier matrix



$$\mathbf{p}(t) = \begin{bmatrix} t^3 & t^2 & t & 1 \end{bmatrix} \begin{bmatrix} -1 & 3 & -3 & 1 \\ 3 & -6 & 3 & 0 \\ -3 & 3 & 0 & 0 \\ 1 & 0 & 0 & 0 \end{bmatrix} \begin{bmatrix} \mathbf{p}_0 \\ \mathbf{p}_1 \\ \mathbf{p}_2 \\ \mathbf{p}_3 \end{bmatrix}$$

– note that these are the Bernstein polynomials

$$C(n,k) t^k (1-t)^{n-k}$$


and that defines Bézier curves for any degree

## Bézier basis



## Convex hull

- If basis functions are all positive, the spline has the convex hull property
  - we're still requiring them to sum to 1




- if any basis function is ever negative, no convex hull prop.
  - proof: take the other three points at the same place

## Chaining spline segments

- Hermite curves are convenient because they can be made long easily
- Bézier curves are convenient because their controls are all points and they have nice properties
  - and they interpolate every 4th point, which is a little odd
- We derived Bézier from Hermite by defining tangents from control points
  - a similar construction leads to the interpolating *Catmull-Rom* spline


## Chaining Bézier splines

- No continuity built in
- Achieve  $C^1$  using collinear control points



## Subdivision

- A Bézier spline segment can be split into a two-segment curve:




- de Casteljau's algorithm
- also works for arbitrary  $t$

## Cubic Bézier splines

- Very widely used type, especially in 2D
  - e.g. it is a primitive in PostScript/PDF
- Can represent  $C^1$  and/or  $G^1$  curves with corners
- Can easily add points at any position
- Illustrator demo

## Hermite to Catmull-Rom

- Have not yet seen any interpolating splines
- Would like to define tangents automatically
  - use adjacent control points



- end tangents: extra points or zero

## Hermite to Catmull-Rom

- Tangents are  $(\mathbf{p}_{k+1} - \mathbf{p}_{k-1}) / 2$ 
  - scaling based on same argument about collinear case

$$\mathbf{p}_0 = \mathbf{q}_k$$


$$\mathbf{p}_1 = \mathbf{q}_{k+1}$$

$$\mathbf{v}_0 = 0.5(\mathbf{q}_{k+1} - \mathbf{q}_{k-1})$$

$$\mathbf{v}_1 = 0.5(\mathbf{q}_{k+2} - \mathbf{q}_k)$$

$$\begin{bmatrix} \mathbf{a} \\ \mathbf{b} \\ \mathbf{c} \\ \mathbf{d} \end{bmatrix} = \begin{bmatrix} 2 & -2 & 1 & 1 \\ -3 & 3 & -2 & -1 \\ 0 & 0 & 1 & 0 \\ 1 & 0 & 0 & 0 \end{bmatrix} \begin{bmatrix} 0 & 1 & 0 & 0 \\ 0 & 0 & 1 & 0 \\ -.5 & 0 & .5 & 0 \\ 0 & -.5 & 0 & .5 \end{bmatrix} \begin{bmatrix} \mathbf{q}_{k-1} \\ \mathbf{q}_k \\ \mathbf{q}_{k+1} \\ \mathbf{q}_{k+2} \end{bmatrix}$$

## Catmull-Rom basis




## Catmull-Rom splines

- Our first example of an interpolating spline
- Like Bézier, equivalent to Hermite
  - in fact, all splines of this form are equivalent
- First example of a spline based on just a control point sequence
- Does not have convex hull property

## B-splines

- We may want more continuity than  $C^1$
- We may not need an interpolating spline
- B-splines are a clean, flexible way of making long splines with arbitrary order of continuity
- Various ways to think of construction
  - a simple one is convolution
  - relationship to sampling and reconstruction

## Cubic B-spline basis



## Deriving the B-Spline

- Approached from a different tack than Hermite-style constraints
  - Want a cubic spline; therefore 4 active control points
  - Want  $C^2$  continuity
  - Turns out that is enough to determine everything

## Efficient construction of any B-spline


- B-splines defined for all orders
  - order  $d$ : degree  $d - 1$
  - order  $d$ :  $d$  points contribute to value
- One definition: Cox-deBoor recurrence

$$b_1 = \begin{cases} 1 & 0 \leq u < 1 \\ 0 & \text{otherwise} \end{cases}$$

$$b_d = \frac{t}{d-1} b_{d-1}(t) + \frac{d-t}{d-1} b_{d-1}(t-1)$$

## B-spline construction, alternate view

- Recurrence
  - ramp up/down
- Convolution
  - smoothing of basis fn
  - smoothing of curve



## Cubic B-spline matrix

$$\mathbf{p}(t) = [t^3 \quad t^2 \quad t \quad 1] \cdot \frac{1}{6} \begin{bmatrix} -1 & 3 & -3 & 1 \\ 3 & -6 & 3 & 0 \\ -3 & 0 & 3 & 0 \\ 1 & 4 & 1 & 0 \end{bmatrix} \begin{bmatrix} \mathbf{p}_{k-1} \\ \mathbf{p}_k \\ \mathbf{p}_{k+1} \\ \mathbf{p}_{k+2} \end{bmatrix}$$

## Other types of B-splines

- Nonuniform B-splines
  - discontinuities not evenly spaced
  - allows control over continuity or interpolation at certain points
  - e.g. interpolate endpoints (commonly used case)
- Nonuniform Rational B-splines (NURBS)
  - ratios of nonuniform B-splines:  $x(t) / w(t); y(t) / w(t)$
  - key properties:
    - invariance under perspective as well as affine
    - ability to represent conic sections exactly

## Converting spline representations

- All the splines we have seen so far are equivalent
  - all represented by geometry matrices

$$\mathbf{p}_S(t) = T(t)M_S P_S$$

- where  $S$  represents the type of spline
- therefore the control points may be transformed from one type to another using matrix multiplication

$$P_1 = M_1^{-1} M_2 P_2$$



$$\begin{aligned} \mathbf{p}_1(t) &= T(t)M_1(M_1^{-1}M_2P_2) \\ &= T(t)M_2P_2 = \mathbf{p}_2(t) \end{aligned}$$

## Evaluating splines for display

- Need to generate a list of line segments to draw
  - generate efficiently
  - use as few as possible
  - guarantee approximation accuracy
- Approaches
  - recursive subdivision (easy to do adaptively)
  - uniform sampling (easy to do efficiently)

## Evaluating by subdivision

- Recursively split spline
  - stop when polygon is within epsilon of curve
- Termination criteria
  - distance between control points
  - distance of control points from line



## Evaluating with uniform spacing

- Forward differencing
  - efficiently generate points for uniformly spaced  $t$  values
  - evaluate polynomials using repeated differences