Spline Curves

CS 465 Lecture 10

Motivation: smoothness

- In many applications we need smooth shapes
  - that is, without discontinuities

[Boeing]

- So far we can make
  - things with corners (lines, squares, rectangles, …)
  - circles and ellipses (only get you so far!)

Classical approach

- Pencil-and-paper draftsmen also needed smooth curves
- Origin of "spline:" strip of flexible metal
  - held in place by pegs or weights to constrain shape
  - traced to produce smooth contour



Translating into usable math

- Smoothness
  - in drafting spline, comes from physical curvature minimization
  - in CG spline, comes from choosing smooth functions
    - usually low-order polynomials
- Control
  - in drafting spline, comes from fixed pegs
  - in CG spline, comes from user-specified *control points*

Defining spline curves

- At the most general they are parametric curves

$$S = \{\mathbf{p}(t) \,|\, t \in [0, N]\}$$

- Generally *f*(*t*) is a piecewise polynomial
  - for this lecture, the discontinuities are at the integers



Defining spline curves

- Generally *f*(*t*) is a piecewise polynomial
  - for this lecture, the discontinuities are at the integers
  - e.g., a cubic spline has the following form over [k, k + 1]:

$$x(t) = a_x t^3 + b_x t^2 + c_x t + d_x$$
$$y(t) = a_y t^3 + b_y t^2 + c_y t + d_y$$

  - Coefficients are different for every interval

Coordinate functions



Coordinate functions



Control of spline curves

- Specified by a sequence of ***control points***
- Shape is guided by control points (aka control polygon)
  - **interpolating**: passes through points
  - **approximating**: merely guided by points

How splines depend on their controls

- Each coordinate is separate
  - the function $x(t)$ is determined solely by the x coordinates of the control points
  - this means 1D, 2D, 3D, … curves are all really the same
- Spline curves are **linear** functions of their controls
  - moving a control point two inches to the right moves $x(t)$ twice as far as moving it by one inch
  - $x(t)$, for fixed t, is a linear combination (weighted sum) of the control points' x coordinates
  - $\mathbf{p}(t)$, for fixed t, is a linear combination (weighted sum) of the control points

Splines as reconstruction



Trivial example: piecewise linear

- This spline is just a polyline
  - control points are the vertices
- But we can derive it anyway as an illustration
- Each interval will be a linear function
  - $x(t) = at + b$
  - constraints are values at endpoints
  - $b = x_0$; $a = x_1 - x_0$
  - this is linear interpolation



Trivial example: piecewise linear

- Vector formulation

$$x(t) = (x_1 - x_0)t + x_0$$
$$y(t) = (y_1 - y_0)t + y_0$$
$$\mathbf{p}(t) = (\mathbf{p}_1 - \mathbf{p}_0)t + \mathbf{p}_0$$

- Matrix formulation

$$\mathbf{p}(t) = \begin{bmatrix} t & 1 \end{bmatrix} \begin{bmatrix} -1 & 1 \\ 1 & 0 \end{bmatrix} \begin{bmatrix} \mathbf{p}_0 \\ \mathbf{p}_1 \end{bmatrix}$$

Trivial example: piecewise linear

- Basis function formulation
  - regroup expression by **p** rather than *t*

$$\begin{aligned} \mathbf{p}(t) &= (\mathbf{p}_1 - \mathbf{p}_0)t + \mathbf{p}_0 \\ &= (1-t)\mathbf{p}_0 + t\mathbf{p}_1 \end{aligned}$$

  - interpretation in matrix viewpoint

$$\mathbf{p}(t) = \left(\begin{bmatrix} t & 1 \end{bmatrix} \begin{bmatrix} -1 & 1 \\ 1 & 0 \end{bmatrix} \right) \begin{bmatrix} \mathbf{p}_0 \\ \mathbf{p}_1 \end{bmatrix}$$

Trivial example: piecewise linear

- Vector blending formulation: “average of points”
  - blending functions: contribution of each control point as *t* changes



Trivial example: piecewise linear

- Basis function formulation: “function times point”
  - basis functions: contribution of each point as *t* changes



  - can think of them as blending functions glued together
  - (this is just like a reconstruction filter!)

Seeing the basis functions

- Basis functions of a spline are revealed by how the curve changes in response to a change in one control
  - to get a graph of the basis function, start with the curve laid out in a straight, constant-speed line
    - what are $x(t)$ and $y(t)$?
  - then move one control straight up

Hermite splines

- Less trivial example
- Form of curve: piecewise cubic
- Constraints: endpoints and tangents (derivatives)



Hermite splines

- Solve constraints to find coefficients

$$
\begin{aligned}
x(t) &= at^3 + bt^2 + ct + d \\
x'(t) &= 3at^2 + 2bt + c \\
x(0) &= x_0 = d \\
x(1) &= x_1 = a + b + c + d \\
x'(0) &= x'_0 = c \\
x'(1) &= x'_1 = 3a + 2b + c
\end{aligned}
$$

$$
\begin{aligned}
d &= x_0 \\
c &= x'_0 \\
a &= 2x_0 - 2x_1 + x'_0 + x'_1 \\
b &= -3x_0 + 3x_1 - 2x'_0 - x'_1
\end{aligned}
$$

Hermite splines

- **Preview:** Matrix form is much simpler

$$
\mathbf{p}(t) = \begin{bmatrix} t^3 & t^2 & t & 1 \end{bmatrix} \begin{bmatrix} 2 & -2 & 1 & 1 \\ -3 & 3 & -2 & -1 \\ 0 & 0 & 1 & 0 \\ 1 & 0 & 0 & 0 \end{bmatrix} \begin{bmatrix} \mathbf{p}_0 \\ \mathbf{p}_1 \\ \mathbf{v}_0 \\ \mathbf{v}_1 \end{bmatrix}
$$

  - cofficients = rows
  - basis functions = columns
    - note **p** columns sum to $[0\ 0\ 0\ 1]^T$

Longer Hermite splines

- Can only do so much with one Hermite spline
- Can use these splines as segments of a longer curve
  - curve from t = 0 to t = 1 defined by first segment
  - curve from t = 1 to t = 2 defined by second segment
- To avoid discontinuity, match derivatives at junctions
  - this produces a C^1 curve

Hermite splines

- Hermite blending functions



Hermite splines

- Hermite basis functions



Continuity

- Smoothness can be described by degree of continuity
  - zero-order (C^0): position matches from both sides
  - first-order (C^1): tangent matches from both sides
  - second-order (C^2): curvature matches from both sides
  - G^n vs. C^n



Continuity

- **Parametric continuity (*C*):**
  - Continuity of the coordinate functions
- **Geometric continuity (*G*):**
  - Continuity of the curve itself
- Neither form of continuity guarantees the other:
  - Can be C^1 but not G^1 when $\mathbf{p}(t)$ comes to a halt (next slide)
  - Can be G^1 but not C^1 when the tangent vector changes length abruptly

Geometric vs. parametric continuity



Control

- Local control
  - changing control point only affects a limited part of spline
  - without this, splines are very difficult to use
  - many likely formulations lack this
    - natural spline
    - polynomial fits

Control

- Convex hull property
  - convex hull = smallest convex region containing points
    - think of a rubber band around some pins
  - some splines stay inside convex hull of control points
    - make clipping, culling, picking, etc. simpler



YES YES YES NO

Affine invariance

- Transforming the control points is the same as transforming the curve
  - true for all commonly used splines
  - extremely convenient in practice…



Matrix form of spline

$$\mathbf{p}(t) = \mathbf{a}t^3 + \mathbf{b}t^2 + \mathbf{c}t + \mathbf{d}$$

$$\begin{bmatrix} t^3 & t^2 & t & 1 \end{bmatrix} \begin{bmatrix} \times & \times & \times & \times \\ \times & \times & \times & \times \\ \times & \times & \times & \times \\ \times & \times & \times & \times \end{bmatrix} \begin{bmatrix} \mathbf{p}_0 \\ \mathbf{p}_1 \\ \mathbf{p}_2 \\ \mathbf{p}_3 \end{bmatrix}$$

$$\mathbf{p}(t) = b_0(t)\mathbf{p}_0 + b_1(t)\mathbf{p}_1 + b_2(t)\mathbf{p}_2 + b_3(t)\mathbf{p}_3$$

Hermite splines

- Constraints are endpoints and endpoint tangents



$$\mathbf{p}(t) = \begin{bmatrix} t^3 & t^2 & t & 1 \end{bmatrix} \begin{bmatrix} 2 & -2 & 1 & 1 \\ -3 & 3 & -2 & -1 \\ 0 & 0 & 1 & 0 \\ 1 & 0 & 0 & 0 \end{bmatrix} \begin{bmatrix} \mathbf{p}_0 \\ \mathbf{p}_1 \\ \mathbf{v}_0 \\ \mathbf{v}_1 \end{bmatrix}$$

Hermite basis





Affine invariance

- Basis functions associated with points should always sum to 1



$$
\begin{aligned}
\mathbf{p}(t) &= b_0\mathbf{p}_0 + b_1\mathbf{p}_1 + b_2\mathbf{v}_0 + b_3\mathbf{v}_1 \\
\mathbf{p}'(t) &= b_0(\mathbf{p}_0 + \mathbf{u}) + b_1(\mathbf{p}_1 + \mathbf{u}) + b_2\mathbf{v}_0 + b_3\mathbf{v}_1 \\
&= b_0\mathbf{p}_0 + b_1\mathbf{p}_1 + b_2\mathbf{v}_0 + b_3\mathbf{v}_1 + (b_0 + b_1)\mathbf{u} \\
&= \mathbf{p}(t) + \mathbf{u}
\end{aligned}
$$

Hermite to Bézier

- Mixture of points and vectors is awkward
- Specify tangents as differences of points



–Note: derivative is defined as 3 times offset
- reason is illustrated by linear case

Hermite to Bézier

$$
\begin{aligned}
\mathbf{p}_0 &= \mathbf{q}_0 \\
\mathbf{p}_1 &= \mathbf{q}_3 \\
\mathbf{v}_0 &= 3(\mathbf{q}_1 - \mathbf{q}_0) \\
\mathbf{v}_1 &= 3(\mathbf{q}_3 - \mathbf{q}_2)
\end{aligned}
$$

$$
\begin{bmatrix} \mathbf{a} \\ \mathbf{b} \\ \mathbf{c} \\ \mathbf{d} \end{bmatrix} = \begin{bmatrix} -1 & 3 & -3 & 1 \\ 3 & -6 & 3 & 0 \\ -3 & 3 & 0 & 0 \\ 1 & 0 & 0 & 0 \end{bmatrix} \begin{bmatrix} \mathbf{q}_0 \\ \mathbf{q}_1 \\ \mathbf{q}_2 \\ \mathbf{q}_3 \end{bmatrix}
$$

Bézier matrix

$$
\mathbf{p}(t) = \begin{bmatrix} t^3 & t^2 & t & 1 \end{bmatrix} \begin{bmatrix} -1 & 3 & -3 & 1 \\ 3 & -6 & 3 & 0 \\ -3 & 3 & 0 & 0 \\ 1 & 0 & 0 & 0 \end{bmatrix} \begin{bmatrix} \mathbf{p}_0 \\ \mathbf{p}_1 \\ \mathbf{p}_2 \\ \mathbf{p}_3 \end{bmatrix}
$$

– note that these are the Bernstein polynomials

$C(n,k)\, t^k\, (1 - t)^{n - k}$

and that defines Bézier curves for any degree.

– C(n,k): Binomial coefficient $_nC_k \equiv \binom{n}{k} \equiv \frac{n!}{(n-k)!\,k!}$,

Bézier basis





Convex hull

- If basis functions are all positive, the spline has the convex hull property
  - we're still requiring them to sum to 1

  - if any basis function is ever negative, no convex hull property!
    - proof: take the other three points at the same place

Chaining spline segments

- Hermite curves are convenient because they can be made long easily
- Bézier curves are convenient because their controls are all points and they have nice properties
  - and they interpolate every 4th point, which is a little odd
- We derived Bézier from Hermite by defining tangents from control points
  - a similar construction leads to the interpolating *Catmull-Rom* spline

Chaining Bézier splines

- No continuity built in
- Achieve C^1 using collinear control points



Subdivision

- A Bézier spline segment can be split into a two-segment curve:



  - de Casteljau's algorithm (fast, numerically stable)
  - also works for arbitrary *t*

Cubic Bézier splines

- Very widely used type, especially in 2D
  - e.g. it is a primitive in PostScript/PDF
- Can represent C^1 and/or G^1 curves with corners
- Can easily add points at any position
- Illustrator demo

Hermite to Catmull-Rom

- Have not yet seen any interpolating splines
- Would like to define tangents automatically
  - use adjacent control points



  - end tangents: extra points or zero

Hermite to Catmull-Rom

- Tangents are $(\mathbf{q}_{k+1} - \mathbf{q}_{k-1}) / 2$
  - scaling based on same argument about collinear case

$$\begin{aligned}
\mathbf{p}_0 &= \mathbf{q}_k \\
\mathbf{p}_1 &= \mathbf{q}_{k+1} \\
\mathbf{v}_0 &= 0.5(\mathbf{q}_{k+1} - \mathbf{q}_{k-1}) \\
\mathbf{v}_1 &= 0.5(\mathbf{q}_{k+2} - \mathbf{q}_k)
\end{aligned}$$

$$\begin{bmatrix} \mathbf{a} \\ \mathbf{b} \\ \mathbf{c} \\ \mathbf{d} \end{bmatrix} = \begin{bmatrix} 2 & -2 & 1 & 1 \\ -3 & 3 & -2 & -1 \\ 0 & 0 & 1 & 0 \\ 1 & 0 & 0 & 0 \end{bmatrix} \begin{bmatrix} 0 & 1 & 0 & 0 \\ 0 & 0 & 1 & 0 \\ -.5 & 0 & .5 & 0 \\ 0 & -.5 & 0 & .5 \end{bmatrix} \begin{bmatrix} \mathbf{q}_{k-1} \\ \mathbf{q}_k \\ \mathbf{q}_{k+1} \\ \mathbf{q}_{k+2} \end{bmatrix}$$

Catmull-Rom basis



Catmull-Rom splines

- Our first example of an ***interpolating spline***
- Like Bézier, equivalent to Hermite
  - in fact, all splines of this cubic form are equivalent
- First example of a spline based on just a control point sequence
- Does not have convex hull property
- Only C^1

Catmull-Rom Camera Demo



http://www.mvps.org/directx/articles/catmull/

B-splines

- We may want more continuity than C^1
- We may not need an interpolating spline
- B-splines are a clean, flexible way of making long splines with arbitrary order of continuity
- Various ways to think of construction
  - a simple one is convolution
  - relationship to sampling and reconstruction

Cubic B-spline basis



Deriving the B-Spline

- Approached from a different tack than Hermite-style constraints
  - Want a cubic spline; therefore 4 active control points
  - Want C^2 continuity
  - Turns out that is enough to determine everything

Efficient construction of any B-spline

- B-splines defined for all orders
  - order *d*: degree *d* – 1
  - order *d*: *d* points contribute to value
- One definition: Cox-deBoor recurrence

$$b_1 = \begin{cases} 1 & 0 \leq u < 1 \\ 0 & \text{otherwise} \end{cases}$$

$$b_d = \frac{t}{d-1} b_{d-1}(t) + \frac{d-t}{d-1} b_{d-1}(t-1)$$

B-spline construction, alternate view

- Recurrence
  - ramp up/down
- Convolution
  - smoothing of basis fn
  - smoothing of curve



Cubic B-spline matrix

$$\mathbf{p}(t) = \begin{bmatrix} t^3 & t^2 & t & 1 \end{bmatrix} \cdot \frac{1}{6} \begin{bmatrix} -1 & 3 & -3 & 1 \\ 3 & -6 & 3 & 0 \\ -3 & 0 & 3 & 0 \\ 1 & 4 & 1 & 0 \end{bmatrix} \begin{bmatrix} \mathbf{p}_{k-1} \\ \mathbf{p}_k \\ \mathbf{p}_{k+1} \\ \mathbf{p}_{k+2} \end{bmatrix}$$

Other types of B-splines

- Nonuniform B-splines
  - discontinuities not evenly spaced
  - allows control over continuity or interpolation at certain points
  - e.g., interpolate endpoints (commonly used case)
- Nonuniform Rational B-splines (NURBS)
  - ratios of nonuniform B-splines: $x(t) / w(t)$; $y(t) / w(t)$
  - key properties:
    - invariance under perspective as well as affine
    - ability to represent conic sections exactly

Converting spline representations

- All the splines we have seen so far are equivalent
  - all represented by geometry matrices

$$\mathbf{p}_S(t) = T(t) M_S P_S$$

    - where S represents the type of spline
  - therefore the control points may be transformed from one type to another using matrix multiplication

$$P_1 = M_1^{-1} M_2 P_2$$

$$\begin{aligned} \mathbf{p}_1(t) &= T(t) M_1 (M_1^{-1} M_2 P_2) \\ &= T(t) M_2 P_2 = \mathbf{p}_2(t) \end{aligned}$$

Evaluating splines for display

- Need to generate a list of line segments to draw
  - generate efficiently
  - use as few as possible
  - guarantee approximation accuracy
- Approaches
  - recursive subdivision (easy to do adaptively)
  - uniform sampling (easy to do efficiently)

Evaluating by subdivision

- Recursively split spline
  - stop when polygon is within epsilon of curve
- Termination criteria
  - distance between control points
  - distance of control points from line





Evaluating with uniform spacing

- Forward differencing
  - efficiently generate points for uniformly spaced *t* values
  - evaluate polynomials using repeated differences
  - Problem: errors can accumulate